THEDXT

Moving Windows Recovery Partition Correctly

June 10, 2023 by theDXT

Recently I needed to expand a disk on a Windows 10 VM and a Windows Server 2022 VM, but I couldn't because the Recovery Partition was in the way.

When searching for a way to do this I discovered that the internet is full of posts about simply deleting the Windows Recovery Partition. I am not a fan of simply deleting a recovery tool. On numerous occasions the recovery partition has been instrumental in helping me to fix a system.

If you search for how to move the Windows Recovery Partition the internet has many posts of fake ways to do it or ways to do it with third-party tools like GParted. I have nothing against third-party tools or GParted and I don't doubt some of those methods do work. The issue I have with those methods is that you have to take the system offline in order to do them or the tools cost money.

Now yes you could just delete the Windows Recovery partition, but before you do that make sure you understand that you will lose a bunch of recovery options. You can read more about the recovery options you'll lose in an earlier post I made about the Windows Recovery Partition.

Recent Posts

Upgrade Azure AD Connect to Entra Connect Sync
PoE and LLDP
32-bit on Windows 64-bit
Cisco UCS Reset FlexFlash Controller
PowerShell ProgressPreference Issue
VMware vCenter Native Key Provider
Disable Windows Server 2025 Diagnostic Data Screen
Omnissa Horizon Connection Server Backup
Omnissa Horizon Client Default Server
Omnissa Horizon Client prefs.txt

Search

Tags

2014 Calgary Certificates Christmas EUC event

This is what my partitions look like in Disk Management.



We will move the 1 GB recovery partition to the end of the disk allowing us to add the 50 GB of unallocated space to the C drive.

The Process

- Make sure you have a backup of the system you are going to edit the partitions on.
- Open Command Prompt as admin



Run CMD as admin

Disabling The Windows Recovery Partition

How To
Microsoft
Microsoft 365
Mouthy & Keerious
Movie
Networking
podcast
Power Loss
PowerShell
review
Script
Spoiler Free
twelve days of christmas
VEDA
VEDA 2015
video
vlog
Vlog Every Day in April
VMware
Windows
youtube
yyc

```
C:\Windows\system32>reagentc /disable
REAGENTC.EXE: Operation Successful.
```

Disabling the Recovery Partition

The `reagentc /disable` command will disable the recovery partition and will move the recovery partition into a file named `Winre.wim` and will be located in `C:\Windows\System32\Recovery` (you have to enable showing hidden system files if you want to see it)



The Windows Recovery Partition File

DiskPart

- Run the command `diskpart` to launch DiskPart

```
C:\Windows\system32>diskpart

Microsoft DiskPart version 10.0.19041.964

Copyright (C) Microsoft Corporation.
On computer: DXT-HO-PVDI01

DISKPART>
```

Launching DiskPart

- List the disks in your system. You can do this by using the command `list disk`

```
DISKPART> list disk

  Disk ###  Status         Size     Free     Dyn  Gpt
  --------  -------------  -------  -------  ---  ---
  Disk 0    Online          200 GB    50 GB        *

DISKPART>
```

Listing the disks in DiskPart and showing the disk is a GPT disk

Pro tip from Matt in the comments, if there's a * in the column for Gpt that means the disk is likely a GPT disk and if there isn't a * in the Gpt

- Select the disk you need to move the recovery partition on. You can do this by using the command **`select disk`** and the disk number. In my setup disk 0 was the correct disk and the command I entered was **`select disk 0`** .

```
DISKPART> select disk 0

Disk 0 is now the selected disk.
```

Selecting the disk in DiskPart

- List the partitions on that disk. You can do this by using the command **`list partition`**

```
DISKPART> list partition

  Partition ###  Type              Size     Offset
  -------------  ----------------  -------  -------
  Partition 1    System             100 MB  1024 KB
  Partition 2    Reserved            16 MB   101 MB
  Partition 3    Primary            148 GB   117 MB
  Partition 4    Recovery          1024 MB   148 GB
```

Listing the partitions in DiskPart

- Select the recovery partition. You can do this by using the command **`select partition`** and the partition number. In my setup partition 4 is my recovery partition and the command I entered was **`select partition 4`**

```
DISKPART> select partition 4

Partition 4 is now the selected partition.
```

Selecting the partition in DiskPart

The recovery partition is a protected partition so we need to use a bit more force to delete it.

- Force the deletion of the recovery partition. You can do this by using the command **`delete partition override`**

```
DISKPART> delete partition override

DiskPart successfully deleted the selected partition.
```

Disk Management

Now if you look in Disk Management you should no longer have the Recovery Partition and it should show up as unallocated.



Disk Management with the Recovery Partition deleted

- Expand your disk and leave about 1024 MB off your resized size to leave room for the re-enabling the Recovery Partition.



Disk Management should now look something like this.



Disk Management after expanding the disk and leaving room for the Windows Recovery Partition

Once the disk is expanded we need to rebuild everything that is needed for Windows to know that the extra space that we left unallocated can be used to for the recovery partition.

- Create a New Simple Volume with the unallocated space.



Creating a New Simple Volume

- Don’t give it a drive letter.



Not giving the New Simple Volume a drive letter or a drive path

- You can give the new partition a name if you want it does not mater. I'm going to call mine New Recovery.



Naming the New Simple Volume

Disk Management should now look something like this.



Disk Management with the newly created partition that will become the Windows Recovery Partition

Back to DiskPart

- In DiskPart list your partitions again by running the command `list partition`

```
DISKPART> list partition

  Partition ###  Type              Size     Offset
  -------------  ----------------  -------  -------
  Partition 1    System             100 MB  1024 KB
  Partition 2    Reserved            16 MB   101 MB
  Partition 3    Primary            198 GB   117 MB
  Partition 4    Primary           1024 MB   198 GB
```

Listing the partitions with DiskPart

- Select the 1024 MB partition with the command `select partition` and the partition number. In my setup it was partition 4 and the command I ran was `select partition 4`

```
DISKPART> select partition 4

Partition 4 is now the selected partition.
```

Selecting the partition with DiskPart

commands.

GPT disk

On GPT disks we need to change the partition ID to **de94bba4-06d1-4d40-a16a-bfd50179d6ac** which tells Windows that this is a recovery partition

- Run the following command to set the partition as a recovery partition `set id=de94bba4-06d1-4d40-a16a-bfd50179d6ac`



Setting the GPT partition ID in DiskPart

We also need to hide the drive and flag it as a required partition to do that we have to set a GPT attribute to **0x8000000000000001**

- Run the following command to set the GPT attribute to hide the drive and flag it as required
  `gpt attributes=0x8000000000000001`



Setting the GPT attribute in DiskPart

- Now we can exist DiskPart.



Exiting DiskPart

MBR disk

On MBR disks we need to change partition ID to **27** which will tell Windows that this is a recovery partition.

- Run the following command to set the partition as a recovery

```
DISKPART> set id=27

DiskPart successfully set the partition ID.
```

setting the MBR partition ID in DiskPart

- Now we can exist DiskPart.

```
DISKPART> exit

Leaving DiskPart...

C:\Windows\system32>
```

Exiting DiskPart

Enabling The Windows Recovery Partition

- Now we can re-enable the recovery partition by running the command **`reagentc /enable`**

```
C:\Windows\system32>reagentc /enable
REAGENTC.EXE: Operation Successful.
```

Enabling the Windows Recovery Partition

The **`reagentc /enable`** command will copy the **`Winre.wim`** file from **`C:\Windows\System32\Recovery`** into our new recovery partition.



Windows Recovery Partition file is now back on the recovery partition

If you look at Disk Management again everything shows up correctly.



That's all there is to it.

Technically speaking we did just delete the Windows Recovery Partition but we did so in a way to keep our existing recovery partition safely intact and then we rebuild the recovery partition and re-enabled it.

I prefer doing it this way as it leaves your recovery options intact and you can do it all live without any reboots.

If you want to read more about deploying the Windows Recovery Partition you can do so by reading Microsoft's documentation about it.

If you want to read more about reagentc command you do so by reading Microsoft's documentation about it.

Related Posts:

Windows Recovery Partition

ONIE Partition Exists Fix

Reset Windows Password



Disable Windows Server 2025

IT

EUC How To Microsoft Rabbit Hole Recovery Servers Virtual Machines Windows Windows Server

Microsoft 365 Enable Organization Customization

Previous post

Create Active Directory Central Store

Next post

209 responses to “Moving Windows Recovery Partition Correctly”

Dzery August 22, 2023 at 5:37 am

Thank you, I tried your solution and it worked very well. I like it because it does not need third party software and preserves recovery partition. Your description is very clear and detailed.

Reply

Daniel Keer August 22, 2023 at 6:53 am **Post author**

That’s awesome! I’m glad it worked out.

Reply

Steve December 27, 2023 at 8:21 am

Agreed. This saved me a couple of hundred bucks!

Reply

Daniel Keer January 23, 2024 at 10:16 pm **Post author**

Nice!!